



Enabling Workgroup share Windows 7 and Mede8er v2.02

1



Open Control Panel then select Network and Internet

2



Select change advanced sharing settings

Select options as per the screen-shot below

3

Change sharing options for different network profiles

Windows creates a separate network profile for each network you use. You can choose specific options for each profile.

Home or Work (current profile)

Network discovery

When network discovery is on, this computer can see other network computers and devices and is visible to other network computers. [What is network discovery?](#)

Turn on network discovery
 Turn off network discovery

File and printer sharing

When file and printer sharing is on, files and printers that you have shared from this computer can be accessed by people on the network.

Turn on file and printer sharing
 Turn off file and printer sharing

Public folder sharing

When Public folder sharing is on, people on the network, including homegroup members, can access files in the Public folders. [What are the Public folders?](#)

Turn on sharing so anyone with network access can read and write files in the Public folders
 Turn off Public folder sharing (people logged on to this computer can still access these folders)

Media streaming

When media streaming is on, people and devices on the network can access pictures, music, and videos on this computer. This computer can also find media on the network.

Media streaming is off.
[Choose media streaming options...](#)

File sharing connections

Windows 7 uses 128-bit encryption to help protect file sharing connections. Some devices don't support 128-bit encryption and must use 40- or 56-bit encryption.

Use 128-bit encryption to help protect file sharing connections (recommended)
 Enable file sharing for devices that use 40- or 56-bit encryption

Password protected sharing

When password protected sharing is on, only people who have a user account and password on this computer can access shared files, printers attached to this computer, and the Public folders. To give other people access, you must turn off password protected sharing.

Turn on password protected sharing
 Turn off password protected sharing

HomeGroup connections

Typically, Windows manages the connections to other homegroup computers. But if you have the same user accounts and passwords on all of your computers, you can have HomeGroup use your account instead. [Help me decide](#)


Allow Windows to manage homegroup connections (recommended)
 Use user accounts and passwords to connect to other computers

Public

After selection click apply changes tab

SET DRIVE SECURITY

4




Firstly check the Drive that contains the Folder in that you intend to share




Right click

5




Click the "Security" tab and check that "Users" are on the security list. If "Users" are on the list then select "Cancel" and go the folder sharing point 10. If "Users" are not on the list then go to point 6 and select the "Add" tab


6



7




8



Type "users" and select "Check Names" tab


9



Win7 will check the names and display the result. Your result should look like this

PCNAME XXX\Users


10



Select "Apply"

SET FOLDER SHARING


11




Right click the folder you want to share. Place your cursor over the "Share With" text and then select "Specific People".



Right click




12





Type "everyone" in the text input panel and then click "Add"

13



Set folder permission for Read only or Read/Write or remove



- Make sure the Mede8er is connected to your network.
- Go to Media Library 1
- Select Network
- Select Workgroup
- Select the PC you want to stream from
- Select the shared folder